

Create a new ICCF procedure (example: FAQs) that consists of the following:

```
&&OPTIONS 0010011
/INP NOPROMPT
&@MACRO
&@NOPRINT
&/LOAD FAQSICX PARM='&&PARAM1                &&PARAM2'
&/OPTION GETVIS=P-32K
&/UPSI 01010100
/END
/PEND
/RUN
```

To access FAQs via ICCF, enter: FAQS <command>

The passed command must be within quotes if it contains any spaces or commas. Examples of use:

```
FAQS 'D LST,TEST*'
```

```
FAQS MENU
```

NOTE: The above requires BF53122 is applied prior to use.

For use of terminal model 3, 4, or 5 from the ICCF transaction set the following UPSI switches:

Model 5	100xxxxx
Model 4	010xxxxx
Model 3	001xxxxx
Model 2	000x0xxx
Model 1	000x1xxx

In addition, for color or APL support, include these switches:

Extended color	UPSI xxx1xxxx
APL support	UPSI xxxxx1xx

Example from above:

```
&/UPSI 01010100
```

would be MOD4, extended color and APL supported

The BIM-FAQS/ASO timed redisplay function is not supported under ICCF. You must press ENTER to update the current console display.

You must also run FAQSMAIN in a VSE partition, which communicates with the ICCF pseudo partition.