




Maximo 7.6.1.2 Enhancements

Sept 16, 2020

Presenting Today from Cohesive Solutions



Tori Foley – Maximo Consultant




Matt Logsdon – EVP

IBM Released Maximo 7.6.1.2 on July 24, 2020

Maximo EAM Release Lifecycle Timeline

7.6.0 Announced December 2014 – proposed EOS effective date September 2021



IBM Software Lifecycle : <https://ibm.biz/BdidVf>

Notice: IBM's statements regarding its plans, directions, and intent are subject to change or withdrawal at IBM's sole discretion. Information regarding potential future products is intended to outline our general product direction and it should not be relied on in making a purchasing decision. The information mentioned regarding potential future products is not a commitment, promise, or legal obligation to deliver any material, code or functionality. Information about potential future products may not be incorporated into any contract. The development, release, and timing of any future features or functionality described for our products remains at our sole discretion.

Maximo 7.6.1

Core Solution

Maximo
EAM



Industry Solutions

Maximo for Transportation

Maximo for Nuclear
Cal

Maximo for Life Sciences
Cal

Maximo for Utilities
Spatial

Maximo for Oil & Gas
HS&E

Maximo for Aviation

Maximo for Civil Infrastructure

Add-on Solutions

Maximo Scheduler

Maximo Service Provider
(managed/internal)

Maximo Asset Configuration Manager

Maximo Spatial

Maximo Anywhere

Maximo Health, Safety & Environment

Maximo Scheduler Optimization

Maximo ERP Adapter for SAP

Maximo ERP Adapter for Oracle

Maximo Calibration

Maximo Linear

Maximo Archiving

Integrations

IBM Cognos Analytics

IBM Control Desk

Maximo Safety

Maximo MRO Inventory Optimization

Maximo Monitor

Maximo Health

Maximo Predict

Maximo Assist (AI/AR)

All this will be called:

**Maximo
Manage**

(released as part of IBM's "Maximo Application Suite" V8)

Integrations

IBM
Cognos Analytics

IBM
Control Desk

Maximo
Safety

Maximo
MRO Inventory
Optimization

Maximo
Monitor

Maximo
Health

Maximo
Predict

Maximo
Assist (AI/AR)

Maximo Application Suite Products

Maximo 7.6.1.2

- 600 APARs (Authorized Program Analysis Report) Addressed

Application	# of APARs Addressed
Work Order Tracking	52
Graphical Scheduling	47
Graphical Assignment	32
All Applications	30
System User Interface	26
Assets	17
Service Requests	16
Purchase Orders	15
Work Execution	15
Report	14
System Object	13
Start Center	12
Integration Modules	11
System Object Security Scans	10




Two Maximo User Interfaces

Maximo

Classic

Work Centers




Architecture Comparison

Maximo Work Centers




html

Maximo Classic



html





Enhancements to Maximo Classic Applications

1. Add Multiple Attachments
2. New Drilldown Capability
3. Storeroom Hierarchies
4. Push Notification Administration
5. Set or Modify E-Signature Key to User Profile
6. Embedded Email Images Support
7. Importing Data from IBM's Digital Twin Exchange

Enhancements to Maximo Work Center Applications

1. Design Mode for Work Centers

2. Work Center Administration Enhancements

- a. Service Request Default Properties
- b. Guest URL Set Up
- c. IOT Connector Tab

3. Work Execution

- a. Support for Multiple Assets & Locations
- b. Task Sequence Displayed on Card
- c. Ability to Add Classification to Work Orders
- d. Report Work Icon Displayed on Every Card for APPR Work Orders
- e. Ability to Report Time/Labor for Others
- f. Ability to Complete Work for the Crew Provided you are a member of the Crew.
- g. New E-Sig Options

4. Work Execution & Work Supervision

- a. Ability to set Default Work Order Status
- b. URL Attachment Support
- c. Enhanced Service Address Capability

5. Work Supervision

- a. Ability to Make Crew Assignments

6. Inventory Work Center Enhancements

- a. Pick & Stage Capability
- b. Barcode Enablement

Add Multiple Attachments

Create a File Attachment

Only files with the following formats can be enabled for printing: .pdf, .xls, .csv, .txt, .doc, .gif, .jpg, .ppt. Clear the check box beside the Print attached document with report if printable type option (Advanced Option) if the file being attached is not in one of these formats.

+ Select a Folder:

Attachments ▼

Select Files

Name the document:


Advanced Options ⓘ

Copy document to the default location set by your administrator (recommended)? ☒

Add document to the document library for others to use? ☐

Print attached document with report if printable type? ☒

OK **Cancel**



Select Multiple Files

New Drilldown Capability

In 7.6.1.1 and older

Drilldown

Select ⓘ to show children. Select ▼ to hide children. Select ↗ to return location / asset.

Locations

Assets

Location:
BOILER

Boiler Room

Status:
OPERATING

Site:
BEDFORD

Asset in Location:

No assets found at this location.

System
PRIMARY

Show All Systems

Show Path to Top

View Work Details

NEEDHAM:Needham Site

BOILER:Boiler Room

BR200:HVAC System- Main Office

BR210:Circulation Fan #1- Main Office HVAC

BR240:Circulation Fan #2- Main Office HVAC

BR250:Circulation Fan #3- Main Office HVAC

BR230:Boiler Room Emergency Generator

BR300:Boiler Room Reciprocating Compressor

BR400:Main Boiler- 50,000 Lb/Hr

Cancel

Optional New Drilldown in 7.6.1.2 and beyond

Drilldown

NEEDHAM - Needham Site - OPERATING

BOILER - Boiler Room - OPERATING

BR200 - HVAC System- Main Office - OPERATING

BR210 - Circulation Fan #1- Main Office HVAC - OPERATING

BR240 - Circulation Fan #2- Main Office HVAC - OPERATING

BR250 - Circulation Fan #3- Main Office HVAC - OPERATING

11200 - HVAC System- 50 Ton Cool Cap/ 450000 Btu Heat Cap -

11210 - Circulation Fan- Centrifugal/ 20/000 CFM - FACILITIES

11240 - Circulation Fan- Centrifugal/ 20/000 CFM - FACILITIES

11250 - Circulation Fan- Centrifugal/ 20/000 CFM - FACILITIES

IC-11200 - HVAC Quarterly Inspections & Certification

560-00 - Tubing, Copper-1 In ID X .030 In Wall - 25.0

BR230 - Boiler Room Emergency Generator - OPERATING

BR300 - Boiler Room Reciprocating Compressor - OPERATING

BR400 - Main Boiler- 50,000 Lb/Hr - OPERATING

FLTGAR - Fleet Garages - OPERATING

OFFICE - Office Building - Address Unit #2010 Oak St. - OPERATING

PACKAGE - Packaging Department - OPERATING

PLANT-P1 - Materials Processing Plant #1 - OPERATING

SHIPPING - Shipping and Receiving Department - OPERATING

IC-67671 - Fire Extinguisher Inspection and Certificate

Drilldown

PRIMARY

Show all systems

Show path to top

Information

Location:
NEEDHAM

Needham Site

Status:
OPERATING

Operating

Type:
OPERATING

Item:

Meter Group:



View Work Details

OK

Cancel

Enabling Maximo's New Drilldown Capability

- To enable it change this System Property:
mxe.webclient.extendedDrilldown = true
- It is enabled for all users who have access to Open Drilldown.
- Through Security settings you can remove the ability to Move/Modify Asset.
- Locations are shown in **RED**.
- Assets are show in **BLUE**.
- PM's are indicated with this icon: 
- Inventory/Spare Parts are indicated with this icon: 
- The OK button changes when something is selected to allow more options:
- Valid moves are shown in **GREEN**:
- Invalid moves are shown in **RED**:



View Item Availability from the Drilldown

The screenshot displays a software interface with a drilldown menu on the left and a detailed item information panel on the right.

Drilldown Menu (Left):

- OFFICE - Office Building - Address Unit #2010 Oak St. - OPERATING
- PACKAGE - Packaging Department - OPERATING
- PLANT-P1 - Materials Processing Plant #1 - OPERATING
- SHIPPING - Shipping and Receiving Department - OPERATING
- 12100 - Forklift #1 -
 - IC-12100 - Forklift #1 Quarterly Inspection and Certification
 - 43992 - Tire, Forklift- TR-70 - 4.0** (highlighted with an orange box)
 - 12200 - Overhead Crane #1
 - 12300 - Electric Cart -
 - 12400 - Forklift #2 -
 - 12500 - Overhead Crane #2 -
 - 12600 - Conveyor System #1 -
 - 12700 - Conveyor System #2 -
 - PM4287 - Inspect Packaging Machine
 - PM6758 - Maintenance of WINS and DHCP Server
 - IC-67671 - Fire Extinguisher Inspection and Certificate

Information Panel (Right):

AIR
CSELECSY
CSGEO
CSPRIM
ELECTRIC

Show all systems
Show path to top

Information

Item:
43992 Tire, Forklift- TR-70

Lot Type:
NOLOT

Issue Unit:


Order Unit:

View Item Availability (button highlighted with an orange box)

OK Cancel

When an Item is selected the **View Item Availability** button appears.

View Work Details from the Drilldown



When a Location, Asset or PM is selected the **View Work Details** button appears.

Show path to top

Information

Location:

SHIPPING

Shipping and Receiving Department

Status:

OPERATING

Operating

Type:

OPERATING

Item:

Meter Group:

View Work Details

View Work Details from the Drilldown

View Work Details

Asset: 11430

Centrifugal Pump 100GPM/60FT HD

Work Scope

Include Children? ☒

Include Ancestors? ☒

☒ Site-Specific
☐ Global

Refresh

Work

Preventive Maintenance

Routes

Collections

Inspections

Work

☒ Filter

>

☐

☐

☐

☐

1 - 10 of 63

☐

☐

☐ Record	Class	Status	Reported Date	Target Start Date	Description	Priority	History?	Is Task?
							N	N
☐ 1024	> WORKORDER	WSCH		3/27/09 6:45 PM	Condensate Return Pump Quarterly Service	6	☐	☐
☐ 42001	> WORKORDER	APPR		10/27/01 3:45 PM	Inspection and Certification	3	☐	☐
☐ 43041	> WORKORDER	APPR		1/1/02 9:45 AM	11430 PM WORK	3	☐	☐
☐ 43042	> WORKORDER	APPR		3/2/02 9:45 AM	11430 PM work jobs	3	☐	☐
☐ 43043	> WORKORDER	APPR		5/1/02 9:45 AM	11430 PM tasks	3	☐	☐
☐ 43044	> WORKORDER	APPR		6/30/02 9:45 AM	11430 PM WORK	3	☐	☐
☐ 43047	> WORKORDER	APPR		1/26/02 9:45 AM	23972 PM WORK	4	☐	☐
☐ 43048	> WORKORDER	APPR		3/17/02 9:45 AM	23972 PM work jobs	4	☐	☐
☐ 43049	> WORKORDER	APPR		5/6/02 9:45 AM	23972 PM tasks	4	☐	☐
☐ 43050	> WORKORDER	APPR		6/25/02 9:45 AM	23972 PM WORK	4	☐	☐

New Drilldown System Properties


1. **mx.webclient.drilldown.fetchsize**

Number of children fetched for each tree node per request

2. **mx.webclient.drilldown.fetchlimit**

Maximum number of children per node type

Default is 50 for both Properties.



In this case the “fetchsize” was set to 2.

Then you can “Load More” up to the “fetchlimit”

Storerooms Hierarchies

The Problem:

In prior versions of Maximo it was not possible to:

1. Manage a hierarchy of Storerooms to describe the physical or reordering relationship between Storerooms.
2. Create Items in multiple Storerooms and update reorder points and other values at one time.
3. Specify that Items in a given Storeroom must be reordered from another Storeroom

Storerooms Hierarchies

The Solution:

Enhancements made to the following applications.

Storeroom Application

1. The ability to assign a **Parent Storeroom**.
2. A new **Reorder From** field has been added to specify where existing Items must be reordered.

Item Master Application

1. A new action to **Add Items to Multiple Storeroom** so that:
 - Items can be added to a Storeroom, a list of Storerooms, or a hierarchy of Storerooms.
 - Reorder settings can be populated considering the Reorder From field when needed.

Organization Application

1. New Item option added to set the maximum number of Items that can be created in the Inventory application from the Item Master application when using the Add Items to Multiple Storerooms action.

Storerooms Hierarchies

Home

Menu

Storerooms

Find Location

Search

Dropdown

Plus

Share

Refresh

Previous

Next

← List View

Storeroom

Items

Location:

SR-MATT1

Matt 1 Store Room

Parent Storeroom:

CENTRAL

>

GL Control Account:

Search

Cost Adjustment Account:

Search

Receipt Variance Account:

Search

Purchase Variance Account:

Search

Recent Lead Time Weight in %:

Site:

BEDFORD

Reorder Storeroom:

Reorder Site:

Shrinkage Account:

Search

Invoice Variance Account:

Search

Currency Variance Account:

Search

Tool Control Account:

Now you can assign a Parent Storeroom

Reorder From Storeroom

Storerooms Hierarchies

Home

Menu

Storerooms

Find Location

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

New Storeroom

Save Storeroom

Clear Changes

More Actions

Select Reorder Storeroom

Delete Storeroom

Add to Bookmarks

List View

Storeroom

Items

Location: SR-MATT1

Matt 1 Store Room

Site: BEDFORD

Parent Storeroom: CENTRAL

GL Control Account:

Cost Adjustment Account:

Receipt Variance Account:

Purchase Variance Account:

Recent Lead Time Weight in %:

Ship to Labor:

Reorder Storeroom: CENTRAL

Reorder Site: BEDFORD

Shrinkage Account:

Invoice Variance Account:

Currency Variance Account:

Tool Control Account:

Default Storeroom?

Which changes this field

New Action to Select Reorder Storeroom

Storeroom Hierarchies – Adding Items to Multiple Storerooms

Item Master

Find Item

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

New Item

Change Status

Create KPI

Create Report

More Actions

Add Items To Storeroom

Add Items to Multiple Storerooms

Unit of Measure and Conversion

Add/Modify Commodity Codes

Attachment Library/Folders

Advanced Search

Items

Filter

Item

0-0031

0-0048

0-0514

0-7205

013

0G3582

1002

10112

10W-30

111-3718

New Action

Storeroom Hierarchies

Specify your hierarchy here then hit Refresh

Add Items Numbers to Multiple Storeroom

Site:
BEDFORD

Top Storeroom in Hierarchy:

Refresh

Target Storerooms

☐	Target Storeroom	Description	Parent	Reorder Storeroom	Site
☐	CENTRAL	Central Storeroom			BEDFORD
☐	GARAGE	Garage Storeroom			BEDFORD
☐	HARDWARE	IT hardware components			BEDFORD
☐	HWMCLEAN				BEDFORD
☐	MACHSHOP	Machine Shop Storeroom			BEDFORD
☐	PKG	Packaging Dept. Storeroom			BEDFORD
☐	SOFTWARE	Software License Pool			BEDFORD
☐	SR-MATT1	Matt 1 Store Room	CENTRAL	CENTRAL	BEDFORD
☐	SR-MATT2	Matt 2 Storeroom	SR-MATT1	CFNTRAI	RFDFORD

OK Cancel

Select Multiple Storerooms here

Storeroom Hierarchies

Add Items to Multiple Storerooms

Default Values

Run Storeroom Update in Background?

☐

Notification Email:

mlogsdon@cohesivesolutions.com

The Storeroom Information table shows only the items that do not currently exist in the target storerooms.

Storeroom Information

Filter

>

Q

X

↑

↓

<

1 - 2 of 2

>

Download

☐	Storeroom	Item	Issue Cost Type	Unit Cost	Default Bin	Current Balance	Lot	Issue Unit	Order Unit	Site
☐	▼ SR-MATT1	Q 013	Q AVERAGE	Q 0.00				Q	Q	Q BEDFORD
☐	► SR-MATT2	Q 013	Q AVERAGE	Q 0.00				Q	Q	Q BEDFORD

Details

Reorder Details

Consignment Details

• Storeroom:

SR-MATT1

• Item:

013

ConditionCode:

Site:

BEDFORD

Default Bin:

Stock Category:

STK

Reorder?

☒

• Reorder Point:

0.00

• Lead Time (Days):

0

Manufacturer:

Model:

Catalog #:

Consignment?

☐

Reorder Point can be specified here for each Storeroom

OKCancel

Storeroom Hierarchies

Add Items to Multiple Storerooms

Default Values

Run Storeroom Update in Background?

Notification Email:

mlogsdon@cohesivesolutions.com

 The Storeroom Information table shows only the items that do not currently exist in the target storerooms.

Storeroom Information

Filter

>

</

OK Cancel

Storeroom Hierarchies

Set Default Values Here.

They will be applied to the selected records here.

Add Items to Multiple Storerooms

Default Values

Issue Unit: _____ 🔍	Lead Time (Days): _____	Manufacturer: _____ >	Reorder? _____ 🔍	Consider?
Order Unit: _____ 🔍	Safety Stock: _____	Model: _____	Primary Vendor: _____ >	
Reorder Point: _____	Economic Order Quantity: _____	Catalog #: _____	Internal? _____ 🔍	

Run Storeroom Update in Background? ☐

Notification Email: mlogsdon@cohesivesolutions.com

The Storeroom Information table shows only the items that do not currently exist in the target storerooms.

Storeroom Information	Filter	>	🔍	⌵	↑	↓	←	1 - 3 of 3	→
☐	Storeroom	Item	Issue Cost Type	Unit Cost	Default Bin	Current Balance	Lot	Issue Unit	Order Un
☒	> CENTRAL	🔍 013	🔍 AVERAGE	🔍 0.00				🔍	🔍

Storeroom Hierarchies

Other Features:

1. You can **Invert Selection** under Default Values
2. You can run the **Add Multiple Items to Storerooms** action from the List View

Storeroom Hierarchies – New Organization Setting

Organizations

Find Organization

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

Common Actions

New Organization

Save Organization

Clear Changes

Create Report

More Actions

Service Address Options

Work Order Options

Inventory Options

Crew Assignment Options

Asset Options

List View

Organization

Address

Organization: EAGLENA EAGLE Inc. North Ame

Base Currency 1: USD United States of America

Base Currency 2:

Item Set: SET1 Item set 1

Company Set: COMPSET1 Company set 1

Default Item Status: PENDING

Default Stock Category: STK

Item Options

Create Item in Inventory Option

Maximum Number of Items Created in Inventory:

100

OK

Cancel

Administration – Push Notification Administration

- Anywhere 7.6.4
 - Push Notification Administration App

Push Notification Administration

Find Navigation Item

Go To Applications

Available Queries

All Records

Common Actions

Provider Configuration

View Registered Devices

Save Provider Details

Clear Changes

More Actions

Push Notification Providers

Device Type	Provider Name	Active?
ANDROID	IPN	☒
IOS	APN	☒

New Row

IPN Push Notification Projects for ANDROID

Project name	Description	Active?
There are no rows to display.		

New Row

Push Notification Provider Configuration

Push Notification Providers

Provider Name	Description
APN	Apple Push Notification
FCM	Firebase Cloud Messaging
IPN	IBM Push Notification

Ok Cancel

Administration – Push Notification Administration

■ Notifications App

The screenshot shows the 'Notifications' application in a web browser. The interface includes a top navigation bar with a home icon, a menu icon, and the title 'Notifications'. Below this is a search bar for 'Find Event name' and a navigation bar with 'List View' and 'Notification Events' tabs. The main content area is divided into several sections: 'Event name' (SRNOTF), 'Event Structure' (MXAPISR), 'Apply To Condition' (Notify resolved and closed SRs), 'Message Template' (SRNOTF), and 'Event Conditions' (SRRESOLVED). There are also checkboxes for 'On Add?', 'On Update?', and 'On Delete?'. A 'More Actions' section on the left includes options like 'Add to Bookmarks', 'Notification Message Template', 'Notification User Subscription', 'User Notification', and 'Delete Notification'. At the bottom, there is a table with columns 'Object Name', 'Relationship', and 'Modified Attribute', showing a single row with 'SR' and 'STATUS'. A 'New Row' button is located below the table.

- Anywhere
- Websphere

Set or Modify E-Signature Key added to User Profile (Tori)

Users

Find User

Find Navigation Item

Go To Applications

Available Queries

All Records

All Bookmarks

All User Types

Users with the Status 'BLOCKED'

Common Actions

New User

Save User

Clear Changes

Change Status

Create Report

More Actions

Workflow

View History

Database Access

Set Password Hint

Reset E-Signature Key

User: MAXADMIN

Login Information

User Name: maxadmin

Personal

Person: MAXADMIN

Status: ACTIVE

First Name:

Last Name:

Supervisor:

Sends an email with this info:

Enclosed is your new Maximo Esig key **c23a6kbadh**. To log in and change your key, follow this link:

Default Information

Personal Information

Password Information

Set or Modify E-Signature Key

Status: ACTIVE

Enter the reset key into the current field, then enter your new key

Set or Modify E-Signature Key

User: MAXADMIN MAXADMIN

Current E-Signature Key:

New E-Signature Key:

Verify New E-Signature Key:

OK Cancel

Support for Embedded Email Images in Service Requests

Guard Rail at Compressor Unit 1

maxsupport@cohesivesolutions.com

Guard Rail at Compressor Unit 1


The guard rail around compressor unit 1 is damaged. See picture below.



Images embedded as part of an inbound Service Request email.

Please investigate.

Thank you,
Joe




Support for Embedded Email Images in Service Requests

Service Request Details

Summary: Guard Rail at Compressor Unit 1

Details:



The screenshot shows a rich text editor interface. The toolbar at the top includes icons for undo, redo, cut, copy, paste, bold, italic, underline, strikethrough, bulleted list, numbered list, indent, outdent, link, unlink, image, text color, background color, and a checkmark. Below the toolbar are three dropdown menus: 'Font' (empty), 'Size' (set to 'xx-small'), and 'Format' (set to 'None'). The text area contains the following text:

The guard rail around compressor unit 1 is damaged. See picture below.

[Image 1 saved as attachment Outlook-7799dd007.PNG by e-mail listener.]

[Image 2 saved as attachment Outlook-88987ttrrr2.PNG by e-mail listener.]

Please investigate.

Thank you,
Joe

An orange box highlights the two image placeholder lines, and an orange arrow points from the text 'Currently embedded images are created as Attachments and placed in the document folder.' to the box.

CI

R

Currently embedded images are created as Attachments and placed in the document folder.

When many images like a footer or signature image, its not easy to determine which attachment is the most relevant to the reported issue.

Support for Embedded Email Images in Service Requests

Service Request Details

Summary:
Guard Rail At Compressor Unit 1 

Details:


Font Size Format

The guardrail around compressor unit 1 is damaged. See picture below.



Please investigate.

Thanks you,
Joel

← In 7.6.1.2 the embedded images are shown in context within the body of the email just as they were submitted.

Support for Embedded Email Images in Service Requests

Email Listener needs to be enabled and Maximo needs to be configured to accept Service Requests through emails.

Supported image types include JPEG, PNG, and GIF.

This new behavior is enabled by default, but you can disable it by setting the **mxe.listener.process.cidimages** property to 0.

Importing Data from IBM's Digital Twin Exchange




A Digital Twin is a digital replica of a physical thing.

Like a:

- Pump
- Power Plant
- University Campus
- Offshore Platform

Importing Data from IBM's Digital Twin Exchange



Digital Twins can have many forms.

Importing Data from IBM's Digital Twin Exchange

IBM has a market-place for Digital Twin data called “The Digital Twin Exchange”

The screenshot shows the IBM Digital Twin Exchange homepage. At the top, there's a navigation bar with the IBM Digital Twin Exchange logo and user icons. Below this is a large banner with the heading "Find a Digital Twin" and a subtext explaining the platform's purpose. A search bar is positioned below the banner. The main content area is divided into three columns: "Highest Rated Twin", "Featured Digital Twins", and "Recently Added". Each column displays a digital twin product with an image, title, description, and price.

IBM Digital Twin Exchange

Find a Digital Twin

Leverage the IBM Digital Twin Exchange for easy access to digital twin data for equipment, facilities and IoT. The Digital Twin Exchange is now open to share digital twin downloads to make it easier to manage connected assets, equipment, and internet of things solutions.

What are you looking for today?

Highest Rated Twin

Cat 730 Artic Truck
BILL OF MATERIALS

Caterpillar 730 Articulated Haul Truck – Major Component BOM Pack

\$4,995

Featured Digital Twins

Isolation Forest Anomaly Detection Model

\$0

Cat 994K Wheel Loader
BILL OF MATERIALS

Caterpillar 994K Wheel Loader – Major Component BOM Pack

\$5,395

Recently Added

Heatmaster


\$0

Importing Data from IBM's Digital Twin Exchange

What kind of digital data will you find on IBM's Exchange?

- Bill of materials
- Parts list
- User manuals
- Engineering manuals
- Fault codes
- 2D/3D CAD files
- AR/VR models
- Maintenance manuals
- Maintenance plans
- Operating model
- Remote procedures for the technician of the future
- Stocking strategy
- Forecast model
- Building information models (BIM)
- Service manual

Importing Data from IBM's Digital Twin Exchange



New Action in the Asset Application
to:

“Import Digital Data”

Importing Data from IBM's Digital Twin Exchange

Enter your IBM Digital Twin Exchange Login Credentials

Then hit Request Data

Import Digital Twin Data

Visit IBM Digital Twin Exchange

✦ Digital Twin Email:

mlogsdon@cohesivesolutions.cc

✦ Key:

.....

Filter by Name:

Request Data

Digital Data

0 - 0 of 0

☐ Product ID	Name	Image	Status
There are no rows to display.			

Import Data

Close

Importing Data from IBM's Digital Twin Exchange

Import Digital Twin Data

[Visit IBM Digital Twin Exchange](#)

♦ **Digital Twin Email:** ♦ **Key:**

Filter by Name:

Digital Data 1 - 3 of 3

☐ Product ID	Name	Image	Status
☐ DT-67-253097	Bradford White		
☒ DT-15-245994	Data Sciences Group Job Plans Digital Downloads		
☒ DT-15-245772	Asset Monitor Robotic Twin Simulator and Dashboard		

Your Digital Twin Purchases will show up here.

Select the one you want to import.

Then hit Import Data.

Importing Data from IBM's Digital Twin Exchange

The screenshot shows the 'System Properties' window with a sidebar on the left and a main table of properties. The sidebar includes sections for 'Find Navigation Item', 'Go To Applications', 'Available Queries', 'Common Actions' (with buttons like 'Save Property', 'Clear Changes', 'Live Refresh', etc.), and 'More Actions'. The main table has columns for 'Property Name', 'Description', and 'Current Value'. The 'mxe.dtendpoint' row is highlighted with an orange box, and an orange arrow points from the text below to this row.

Property Name	Description	Current Value
mxe.app.assetcat.addToItemSpecForView	Add the new attribute to ItemSpec for the view	0
mxe.crontask.corethreadtimeout	Policy to determine if core threads in process	
mxe.db.DB2LDTextCaseInsensitiveSearch	When set to 1, DB2 search on LD field is case insensitive	0
mxe.dm.collvalidtgtexclude	Specify target object and attribute combinations to exclude	MAXINTOBJECT.USEWITH,MAXRELATIONSHIP.CARDINALITY
mxe.dtassetaction	The data processing action for the asset	merge
mxe.dtendpoint	The digital twin API endpoint.	https://digitaltwinexchange.ibm.com
mxe.dtbodyplanaction	The data processing action for the job plan	merge
mxe.dtprefix	The prefix for the digital twin data.	DT-

System Property to point to the IBM Digital Twin Exchange.

Enhancements to Maximo Work Center Applications

1. Design Mode for Work Centers

2. Work Center Administration Enhancements

- a. Service Request Default Properties
- b. Guest URL Set Up
- c. IOT Connector Tab

3. Work Execution

- a. Support for Multiple Assets & Locations
- b. Task Sequence Displayed on Card
- c. Ability to Add Classification to Work Orders
- d. Report Work Icon Displayed on Every Card for APPR Work Orders
- e. Ability to Report Time/Labor for Others
- f. Ability to Complete Work for the Crew Provided you are a member of the Crew.
- g. New E-Sig Options

4. Work Execution & Work Supervision

- a. Ability to set Default Work Order Status
- b. URL Attachment Support
- c. Enhanced Service Address Capability

5. Work Supervision

- a. Ability to Make Crew Assignments

6. Inventory Work Center Enhancements

- a. Pick & Stage Capability
- b. Barcode Enablement

General Comment on Maximo Work Centers

- Major Area of Focus for IBM.
- In Maximo 7.6.1.2 and earlier used **Google Polymer** under the hood.
- IBM is replacing **Google Polymer** with technology based on **React Carbon Design Components** which IBM refers to as “**Graphite**”.

Current guidance from Cohesive...

- Use the existing Work Centers as they are out of the box. Don't invest in configuring them.
- Use Google Chrome when working with Work Centers.
- Work Centers will be much improved once they are released on the Graphite platform.

My Start Center Setup

Home

Menu

Welcome, Matt Logsdon

Find Navigation Item

Go To Applications

My Recent Applications

Administration

Analytics

Assets

Building Information Model...

Change

Contracts

Financial

Integration

Inventory

IT Infrastructure

Planning

Planning and Scheduling

Preventive Maintenance

Purchasing

Release

Security

Self Service

Service Desk

Service Level

System Configuration

Task Management

Work Orders

My Maximo Classic Applications

Assets

Locations

Inventory

Storerooms

Item Master

Job Plans

Preventive Maintenance

Work Order Tracking

Service Requests

System Properties

Maximo Work Centers

Administration

Submit a Service Request

Work Execution

Work Supervision

Manage Inspection Forms

Conduct an Inspection

Business Analysis

Manage Inventory

Design Data Sets

Maximo Management Interface

KPI Graph

This portlet has not been set up. To set up, select the edit icon in the portlet header.

Bulletin Board

Filter

To filter for specific records, specify data in the filter fields and then press the Enter key.


Subject	Message	Post Date	Expiration
There are currently no bulletin board messages.			

Result Set

Filter

Chart Type: PIE

All Assets (By Status)



Status	Count
Dark Blue	679
Light Blue	467
White	8
Grey	9

List View

Inbox / Assignments

No Assignments found for Matt Logsdon

KPI Graph

This portlet has not been set up. To set up, select the edit icon in the portlet header.

My Start Center Setup

Portlet: Favorite Applications

Display Name: Favorite Applications

Application Type: ☐ Maximo Classic Application
☐ Work Center or Tools and Tasks

Select Which Type of Application Here

Applications [Filter](#) > 🔍 ⌵ ⬆ ⬇ ⬅ 0 - 0 of 0 ➡ ⬇

Application	Description	Order
 There are no rows to display.		

Finished

Cancel

Select Applications

Design Mode for Work Centers

This icon turns Design Mode On.

IBM Maximo Asset Management

Work Execution



My Work Orders

Overdue (177)

Today (0)

Tomorrow (0)

Next 3-5 Days (0)

Completed (0)

All (184)

Search

Priority

Create work

Alex Smoke Test A10002 WAPPR Asset Description:: Centrifugal Pump 100GPM/60FTHD Location: BR450 Scheduled Start: <i>Unspecified</i> Report Work	New WO from Work Center CM A10025 APPR Asset Description:: Centrifugal Pump 100GPM/60FT HD Location: BR430 Scheduled Start: <i>Unspecified</i> Report Work	Test Work Order 2020 A10048 WAPPR Asset Description:: HVAC System- 50 Ton Cool Cap/ 450000 Btu Heat ... Location: BR200 Scheduled Start: <i>Unspecified</i> Report Work	11450 BREAKDOWN EM 91091 APPR Asset Description:: Centrifugal Pump 100GPM/60FTHD Location: BR450 Scheduled Start: <i>Unspecified</i> Report Work
Generator Overhaul CM 1004 INPRG Asset Description:: Emergency Generator Location: BR230 Scheduled Start: <i>Unspecified</i> Report Work	Water spillage EM 1219 WAPPR Asset Description:: HVAC System- 50 Ton Cool Cap/ 450000 Btu Heat ... Location: BR200 Scheduled Start: <i>Unspecified</i> Report Work	HVAC overheating EM 1225 WAPPR Asset Description:: HVAC System- 50 Ton Cool Cap/ 450000 Btu Heat ... Location: BR200 Scheduled Start: <i>Unspecified</i> Report Work	HVAC overheating CP 1227 WAPPR Asset Description:: HVAC System- 50 Ton Cool Cap/ 450000 Btu Heat ... Location: BR200 Scheduled Start: <i>Unspecified</i> Report Work
HVAC overheating FM 1231	HVAC overheating FM 1232	HVAC overheating FM 1238	HVAC overheating FM 1243

Design Mode for Work Centers

Assets x demo7610.cohesive x My account | IBM Dig x Start Center x IBM Maximo Asset M x Data Sciences Group x

Not secure | 192.168.50.236/maximo-x/#/technician/

IBM Maximo Asset Management Work Execution

Design mode is on

My Work Orders

Overdue (0) Today (0) Tomorrow (0) Next 3-5 Days (0) Completed (0) All (0)

Search

Next 3-5 Days

Priority

description
worktype wonum
status
Asset Description: asset.description
Location: asset.location
Scheduled Start: schedstart_localized

Priority:

Confirmation that
Design Modes is
On.

Hover to expose
Yellow highlighted
area which can be
edited.

Design Mode for Work Centers

Work Execution

Design work panel

* Name ☒ Display? [Get help](#)

Define query

☐ Object structure query

☐ Saved query

☐ REST query

☒ Object structure and REST query

☐ Saved query and REST query

Object structure query

REST query

Time line attribute Time line range

Where clause

```
{ "qbewhere": { "siteid": { "operator": "=", "value": "-dfltsite-"}, "status": { "operator": "in", "valueset": [ "APPR", "WPCOND", "HISTEDIT", "INPRG", "WAPPR", "WMATL", "WSCH" ] } } }
```

Additional parameters

☒ Test query [Reset](#) [Cancel](#) [Save](#)

Edit Query Definition

Design Mode for Work Centers

CAUTION:
Make sure you use
the Chrome
browser!

Design card

description
worktype wonum
status
Asset Description: asset.description
Location: asset.location
Scheduled Start: schedstart_localized

Priority:

Search for field value

Search

Show only required database fields

Objects	Relationships	Fields
WORKORDER		ACTLABCOST Actual Labor Cost
ACTION		ACTLABHRS Actual Labor Hours
ASSET		ACTMATCOST Actual Material Cost
CALENDAR		ACTSERVCOST Actual Service Cost
CI		ACTTOOLCOST Actual Tool Cost
CLASSSTRUCTURE		AMS Requires Asset Maintenance Window
CONTCOMMODITY		AOS
FAILURECODE		
FAILUREREMARK		
INCIDENT		

Cancel Save

Drag Desired Fields

Design Mode for Work Centers

Hit this Icon to Exit
Design Mode

IBM Maximo Asset Management

Work Execution

Design mode is on

My Work Orders

Overdue (0) Today (0) Tomorrow (0) Next 3-5 Days (0) Completed (0) All (0)

Priority

description

worktype wonum

status

Asset Description: asset.description

Location: asset.location

Scheduled Start: schedstart_localized

Priority:

Manage Work Center configuration

Current version

StatusActive

Version Date9/3/20 1:04 PM

Modified ByWILSON

Comments

More actions

View revision history

Save as draft

Publish as active workcenter

Close

Exit design

Options

Design Mode for Work Centers

The screenshot shows the 'Security Groups' application interface. On the left is a sidebar with navigation items like 'Find Group', 'Find Navigation Item', 'All Records', 'All Bookmarks', 'Common Actions', and 'More Actions'. The main area displays a table of applications. The first table, 'Applications', has columns for Description, Application Type, Main Object/Table, and Original Application (if copied). It lists several work centers, with 'Work Execution' highlighted. Below this is a section for 'Options for Work Execution' with buttons like 'Add/Modify Signature Options', 'Manage/Apply Template', 'Object Structure Authorizations', and 'Revoke All Options for This Application'. The second table, 'Options for Work Execution', has columns for Description, Grant Access?, and Condition. It lists several options, with 'Design Work Execution' highlighted and circled in orange. An orange arrow points to this row.

Description	Application Type	Main Object/Table	Original Application (if copied)
Administration	Work Center		
Business Analysis	Work Center		
Manage Inventory	Work Center		
Work Execution	Work Center		
Work Supervision	Work Center		

Description	Grant Access?	Condition
Access to Work Execution	☒	
Add Classification	☒	
Design Work Execution	☒	
Premium code	☒	
Report other labor	☒	

Go to Security Groups and Grant Access to:

- Design Work Execution
- Design Work Supervision
- Etc.

Work Center Enhancements - Service Request Configuration

Default Properties

- Administration > Administration (Two New Tabs)

IBM Maximo Asset Management Administration

Service Request Configuration

Properties Categories Guest URL

You can modify default values for certain attributes which are used when creating Service Requests using Work Centers. These must be valid values already established in Maximo.

Reported priority: - 3 +

High Priority: - 2 +

Filter on person site?: ☐

Source: SRWC

"Describe the Issue" class structure ID: RESTROOMS

Cancel Save

If the MGUEST user is associated with a SITE this toggle will filter Classifications, Locations and Assets for that SITE.

- Strongly recommend Google Chrome when working with Work Centers

Work Center Enhancements - Service Request Configuration

Guest URL Set Up

The screenshot shows the IBM Maximo Asset Management Administration interface. The page title is "Service Request Configuration" with tabs for "Properties", "Categories", and "Guest URL". The "Guest URL" tab is selected and highlighted with an orange box. Below the tabs, a text box explains: "To allow individuals in your organization to submit service requests as a guest using only a valid email address, distribute the guest URL below." Below this, a text box displays the "Your Guest URL:" as `http://192.168.50.236/guest?apiKey=37er8gb099crletlsl5p18sp2fl5ihg20uf3dn6l`, which is also highlighted with an orange box. A "Copy to clipboard" button is next to the URL. To the right of the URL box is a large QR code. Below the URL box, the section "Who can submit a service request?" has two radio button options: "Anyone who works for a trusted company." (unselected) and "A specific list of people." (selected). To the right of these options, a list of email addresses is shown, each with a minus icon to its left: `ALEXSZARO@COMCAST.NET`, `JLONJIN@COHESIVESOLUTIONS.COM`, `MAXIMOMATT@GMAIL.COM`, and `MLOGSDON@COHESIVESOLUTIONS.COM`. Below the list is an "Enter email" input field and an "Add" button. A note above the list states: "* Email (Example: user@abccompany.com) Users can add service requests if they use one of the following email addresses."

- The Guest URL is automatically generated the 1st time the Administrator opens the Guest URL page.
- SR's submitted with this guest URL will have MGUEST as the REPORTEDIN and AFFECTEDPERSONID
- Be sure "maximo-x" is added to the URL string after the domain name.

Work Center Enhancements - Service Request Configuration

Guest User Login

IBM Maximo

Enterprise Asset Management

**You have reached the guest login page for Maximo.
To submit a service request, enter a valid email
address and click the Sign in button.**

Guest Email

Sign in

← Guest User Login Screen

Work Center Enhancements - Service Request Configuration

Categories Tab Remains Unchanged

IBM Maximo Asset Management Administration

Service Request Configuration

Properties **Categories** Guest URL

You can add, modify, or delete category hierarchies for service requests here.

Category +	Sub-Category +	Issue +
Swimming Pool	Filter Issue	Water is not clear.
Keys	Pump Issue	Dirt on bottom of pool.
Landscaping	Pool Deck Issue	Debris floating in pool.
Security	Water Issue	
Restrooms		
Outdoor		
Offices & Cubes		

- Classifications and Ticket Templates are created behind the scene.
- Optional Image can be added within Classifications.

IoT Connector Capability

IBM Maximo Asset Management

Administration

Integration

Message Templates

API Keys

IoT Connector

IoT Connection Service

Associate Devices

Configure Integration

Select IoT Service

Configure IoT Service

Configure End Points

Register Device Types

Map Data Schemas

Select an IoT Service (Step 1 of 5)

Select or add an IoT service.

IoT Service

☐ IBM Watson IoT Platform (IoT Service: IIOTP End Point Name: IBMIOT)

☒ IBM Maximo Asset Monitor (IoT Service: MAXIMO ASSET MONITOR End Point Name: IOTMAM)

☐ AT&T Asset Management Operations Center (IoT Service: ATT_AMOC End Point Name: ATT_AMOC)

+

 Add service

Next >

New Tab.

Click Here


Wizard Set Up

Work Center Enhancements – Work Execution (Technician)

Supports Multiple Assets/Locations

You can open the
Asset and
Location from here

Now supports
Multiple
Assets/Locations



Take
Actions
Here

Work Center Enhancements – Work Execution (Technician)

Supports Task Sequencing

IBM Maximo Asset Management

Work Execution

←

CM ML-MULTIWO

Details

Plans

Comments

Attachments

Tasks (8)

Items and Materials (3)

Tools (0)

Check pump operation.

Task: 10

Owner: Unspecified

Estimated duration: 0:20

ownerGroup: Unspecified

Completetask

Check pump float switch.

Task: 20

Owner: Unspecified

Estimated duration: 0:30

ownerGroup: Unspecified

Completetask

Check housing for leaks.

Task: 30

Owner: Unspecified

Estimated duration: 0:10

ownerGroup: Unspecified

Completetask

Replace mechanical seal.

Task: 40

Owner: Unspecified

Estimated duration: 1:00

ownerGroup: Unspecified

Completetask

Replace contactor & clean contactor c...

Task: 50

Owner: Unspecified

Estimated duration: 1:00

ownerGroup: Unspecified

Completetask

Inspect inpeller for wear

Task: 60

Owner: Unspecified

Estimated duration: 0:10

ownerGroup: Unspecified

Completetask

Record amperage and voltage with mo...

Task: 70

Owner: Unspecified

Estimated duration: 0:10

ownerGroup: Unspecified

Completetask

Inspect main disconnect and all electri...

Task: 80

Owner: Unspecified

Estimated duration: 0:10

ownerGroup: Unspecified

Completetask

Tasks
Sequence #s
are now
displayed

Work Center Enhancements – Work Execution (Technician)

Ability to Add Classification

IBM Maximo Asset Management Work Execution

CM A10025

Details Plans Comments Attachments

New WO from Work Center

longDescription

Status Approved	Priority Unspecified	Asset 11430 Centrifugal Pump 100GP...	Location BR4 Condensate R
Work Type CM Corrective Maintenance	Service Address Unspecified	Classification BEARING \ ... Roller Bearing	Site Bedford MA Site of EAGLE Inc. North America

Classification Close

Search 24 Results

All

BEARING	Select
CUSTODIAL	Select
ELECTRICAL	Select
ELEVATOR	Select
ENGINEERING	Select
FLOWVAL	Select
GROUNDS	Select
HVAC	Select
MECHANICAL	Select
MOTORS	Select
PHYSICAL ENVIRONMENT	Select
PIPE_LEAK	Select
PLUMBING	Select
PUMP	Select
ROAD WORK	Select
SAFETY	Select
SEAL	Select
TANDEM	Select
TRACK INSPECTION DEFECT REPORT	Select
TRACTOR	Select

Select them here

Add Classifications

Work Center Enhancements – Work Execution (Technician)

APPR WO Cards Now Have Report Work Button

IBM Maximo Asset Management

Work Execution

My Work Orders

Overdue (0) Today (1) Tomorrow (24) Next 3-5 Days (25) Completed (0) All (51)

Search

Priority

Create w

New WO from Work Center
CM A10025
APPR
Asset Description: Centrifugal Pump 100GPM/60FT H...
Location: BR430
Scheduled Start: 9/4/20 6:00 AM

Report Work

11450 BREAKDOWN
EM 91091
APPR
Asset Description: Centrifugal Pump 100GPM/60FTHD
Location: BR450
Scheduled Start: 9/4/20 6:00 AM

Report Work

ROUTINE MAINTENANCE
PM 41023
APPR
Asset Description: Burner, Gas Fired- For Boiler
Location: BR400
Scheduled Start: 9/4/20 3:00 AM

Report Work

ROUTINE MAINTENANCE
PM 40092
WAPPR
Asset Description: Burner, Gas Fired- For Boiler
Location: BR400
Scheduled Start: 9/4/20 3:00 AM

Confidential & Proprietary – Copyright 2020

Cohesive
Solutions
A BENTLEY COMPANY

69

Work Center Enhancements – Work Execution (Technician)

Report Labor for Others

IBM Maximo Asset Management

←

Assignments (1)Time (0)Items a

+ Add time

* Matt Logsdon

*Type:
Actual work time ▶

Task:
 Select task

Hours:

-

0:00

+

*Start:
9/3/20 -- : --

End:
- / - / - -- : --

*Craft:
 Select craft

Premium code:
Unspecified

Delete

Save

Report Time/Labor for Others

LaborClose

Search102 Results

Hank Adams
Mechanic
Mechanic 1st Class

Hank Adams
Mechanic
Mechanic 2nd Class

Hank Adams
Mechanic
Mechanic

7.6.1.2 Alex Szaro
Mechanic
Mechanic

Thomas Barry
Mechanic
Mechanic 1st Class

Dave Bethune
Mechanic
Mechanic 1st Class

Dave Bethune
Mechanic
Mechanic 2nd Class

Confidential & Proprietary – Copyright 2020

Cohesive Solutions
A BENTLEY COMPANY

70

Work Center Enhancements – Work Execution (Technician)

Completing Work Order for Crews

IBM Maximo Asset Management

Work Execution

←

Report Work - CM ML-WO10

Assignments (3)

Time (0)

Items and Materials (0)

Tools (0)

Centrifugal Pump Service- 12 Month

Task:
Unspecified

Hours:
3:00

Crew:
Line Crew 101

Scheduledstart:
9/3/20
3:25 PM

Mark complete

Centrifugal Pump Service- 12 Month

Task:
Unspecified

Hours:
2:00

Crew:
Line Crew 101

Scheduledstart:
9/3/20
2:51 PM

Mark complete

If the User is a member of a Crew they can now Complete the Work Order on Behalf of the Crew.

Work Center Enhancements – Work Execution (Technician)

New eSig Options

Work Execution

Work Center

Work Supervision

Work Center

Options for Work Execution

Filter

1 - 1 of 1

Add/Modify Signature Options

Manage/Apply Template

Object Structure Authorizations

Revoke All Options for This Application

Description	Grant Access?	Condition
> Access to Work Execution	☒	>

Filter

1 - 9 of 9


Description	Grant Access?	Condition
> Add Classification	☒	>
> Design Work Execution	☒	>
> Premium code	☒	>
> Report other labor	☒	>

New eSig
Options for
Work
Execution

Work Center Enhancements – Work Execution & Supervision

Set Default WO Status for WO created from Work Centers


Administration > Work Order Options > Site Options



The screenshot shows a dialog box titled "Work Centers" with a close button in the top right corner. Below the title bar, the text "Status for work orders created in Work Execution:" is displayed. There are two radio button options: "WAPPR" (which is selected) and "INPRG". At the bottom right of the dialog box, there are two buttons: "OK" and "Cancel".

Work Center Enhancements – Work Execution & Supervision

Attachments now support URL links.



Work Center Enhancements – Work Supervision

In addition to assigning Labor you can now assign Crews (eSig Option enabled OOTB)

IBM Maximo Asset Management

Details Plans **Assignments** Comments Attachments Reported

Assignments (0)

+ addLabor + Add crew

Work Order on 12300

Task:

Craft:

Electrician - 1st Class

Labor:

Status: Unspecified

Hours: - 1:00 +

Scheduledstart: - / - / -

-- : --

Delete Save

IBM Maximo Asset Management

Details Plans **Assignments** Comments Attachments Reported

Assignments (0)

+ addLabor + Add crew

Work Order on 12300

Crew:

Task:

Crew type:

Hours: - 1:00 +

Crew work group:

Scheduledstart: - / - / -

-- : --

Status: Waiting for Assignment

Delete Save

Ability to
Filter Crews

Filter Settings

* Available from: 9/3/20 * Available until: 9/3/20

Crew work group: Enter crew work group

Vendor: Enter vendor

Include assigned: ☐ No

Inventory Work Center Enhancements – Barcode Icon (Tori)

- Code scanning is available wherever user is selecting bin or item
- Camera opens in video mode
- Red view finder frame is overlaid to help the user focus
- When the code is in focus it snaps to the picture and renders the ID
- An audible beep will sound to indicate success

The screenshot displays the IBM Maximo Asset Management 'Manage Inventory' interface. The top navigation bar includes 'IBM Maximo Asset Management' and 'Manage Inventory'. Below this, there are tabs for 'Reservations', 'Pick and Stage', and 'Issued Items'. The 'Reservations' tab is active. The interface shows search filters for 'From' (1/1/11) and 'To' (9/15/20), with 'Results: 18'. A table header is visible with columns: Type, Date, Work Order, Item, Description, Default Bin, and Quantity. On the right side of the table header, there is a barcode icon highlighted with an orange square, and a magnifying glass icon next to it. The user's location is indicated as 'BEDFORD - CENTRAL'.

Design Mode for Work Centers

IBM Maximo Asset Management

Work Execution

My Work Orders

Overdue (0) Today (0) Tomorrow (0) Next 3-5 Days (0) Completed (0) All (0)

Search

description
worktype wonum
status
Asset Description:: asset.description
Location: asset.location
Scheduled Start: schedstart_localized

Priority:

Design card

description
worktype wonum
status
Asset Description:: asset.description
Location: asset.location
Scheduled Start: schedstart_localized

Priority:

Search for field value

serial

Show only required database fields

Objects	Relationships	Fields
WORKORDER	ASSET	SERIALNUM
ACTION	LINEARASSET	Serial #
ASSET	WO_ASSET	
CALENDAR		
CI		
CLASSSTRUCTURE		
CONTCOMMODITY		
FAILURECODE		
FAILUREREMARK		
INCIDENT		

Cancel

Save

Drag fields from here to your card

Design Mode for Work Centers

When you're finished hit this icon

BM Maximo Asset Management

Work Execution

Design mode is on

My Work Orders

Overdue (0) Today (0) Tomorrow (0) Next 3-5 Days (0) Completed (0) All (0)

Search

Priority

description
worktype wonum
status
Asset Description:: asset.description
Location: asset.location
Scheduled Start: schedstart_localized

Priority:

Manage Work Center configuration

Current version

Status Draft

Version Date 9/2/20 1:52 PM

Modified By MAXIMOMATT

Comments

More actions

View revision history

Save as draft

Publish as active workcenter

Save Options

Close Exit design

Work Center Enhancements – Maximo Management Interface

IBM Maximo Asset Management

Gather Data

☒ Compare

Server Name: MAXIMO

Server Host: 192.168.50.236:13400

Logged In Users: 1

Admin Mode: Off

Application Security: false

Perfmon Running: false

IBM Maximo Asset Management

Maximo Management Interface

Database Information

Mbo Count

Memory

Jvm

Threads

Operating System

Database Information

Product Name: Microsoft SQL Server

Version: 13.00.1742

Release Major Version: 13

Release Minor Version: 0

Maximum Open Statements: 0

Maximum Concurrent Connections: 32767

Driver Name: Microsoft JDBC Driver 7.4 for SQL Server

Driver Version: 7.4.1.0

Release Major Version: 7

Release Minor Version: 4

JDBC Major Version: 4

JDBC Minor Version: 2

Class

Database Management Information

Free Connections: 6

Total Connections: 11

Connections Used: 5

Long Running Connections: 1

Safe Harbor

General Use

The information contained herein is of a general nature and is not intended to address the circumstances of any particular individual or entity. Although we endeavor to provide accurate and timely information, there can be no guarantee that such information is accurate as of the date it is received or that it will continue to be accurate in the future. No one should act on such information without appropriate professional advice after a thorough examination of the particular situation.